

# HEAR HERE

This symbol indicates that a **HEARING LOOP** is available.

Activate the telecoil (t-coil) in your hearing device to hear sound with less background noise — directly into your device.

If you do not have a t-coil enabled device, request a headset + receiver.

For questions about hearing loops and hearing loss contact or visit the Hearing Loss Association of America:

[GITHLinfo@hearingloss.org](mailto:GITHLinfo@hearingloss.org)  
[www.hearingloss.org](http://www.hearingloss.org)



**Hearing Loop**  
Switch hearing aid to T-coil

## A LIFE-CHANGING SOLUTION FOR PEOPLE WITH HEARING LOSS

### HEARING LOOPS

- **Simple** – hearing loops reduce background noise and send sound from a microphone directly to t-coil enabled devices
- **Discreet** – there is no need to ask for additional equipment
- **Effortless** – most hearing devices have an external toggle switch to enable the t-coil

**Talk to your audiologist about t-coil equipped hearing devices. If you already have one of these devices, ask if it is t-coil enabled and learn how to activate the t-coil program.**



Microphone



Hearing Aids  
Cochlear Implants  
Bone Conduction

Toggle to access the t-coil

Hear ALL our Theatre has to offer! We offer a HEARING LOOP Assistive Listening System in our theater. Try it. We are confident you will like it! The hearing loop:



**HEARING LOOP**  
Switch hearing aid or CI to  
t-coil or request headphones

- Streams sound wirelessly to hearing aid/cochlear implant with a telecoil (t-coil).
- People with hearing devices with t-coils don't need to wear and return special equipment. Delivers great sound clarity and ease of listening.

Not sure your hearing devices have a T-coil? Ask your audiologist or hearing aid provider. Most hearing devices have telecoils, but the provider must activate the program.

**Complimentary receivers & headphones available for people without hearing aids/t-coils.**

For more information about the hearing loop, contact us:



GET IN THE  
HEARING  
LOOP

hearingloss.org

## For Audiologists or Hearing Health Care Providers

Please advise me if my hearing devices(s) has a telecoil(s) (t-coil). If they do, please activate and program them for use in a hearing loop. Also, please write instructions for their use on the back of this card. If I don't have a t-coil(s), can it be retrofitted or is there an accessory remote control/streamer telecoil option?

### Program Recommendations

**For open RIC fittings:** manual T only program

**For closed/occluded fittings:** manual M + T program in social settings

**For closed/occluded fittings:** manual T only program for high noise environments like airports or train stations.

Verify mic and telecoil responses **match** in gain, output and frequency response in user programmed mode (use ANSI-SPLIV test procedure).

Programming questions?

**Contact:** Juliëtte Sterkens, AuD, [jsterkens@hearingloss.org](mailto:jsterkens@hearingloss.org)

I would like to use my t-coil(s) in a hearing loop or with a neckloop and an assistive listening device or system.

Please write clear instructions on how to use my manually accessible telecoil program.

For example: the numbered position of the program, number of beeps or voice prompt, and location of the switch to activate the t-coil.



---

Audiologist or hearing health care provider name and contact information